

Project	IEEE 802.16 Broadband Wireless Access Working Group < http://ieee802.org/16 >	
Title	Using Quiet Period for Channel Measurement	
Date Submitted	2006-11-10	
Source(s)	Shulan Feng Hisilicon Tech. Co., LTD Bld.17, No.8, Dongbeiwang West Road, Hai-Dian District, Beijing, P. R. China	Voice: +86-10-82829151 Fax: e-mail to : fengsl@hisilicon.com
Re:	IEEE 802.16 Working Group Letter Ballot #24, on P802.16h/D1	
Abstract	This contribution proposes to perform channel detection using quiet period, including slave sub-frame, extended quiet period and quiet period during CSI/CMI.	
Purpose	Define how to perform channel measure during the operating stage.	
Notice	This document has been prepared to assist IEEE 802.16. It is offered as a basis for discussion and is not binding on the contributing individual(s) or organization(s). The material in this document is subject to change in form and content after further study. The contributor(s) reserve(s) the right to add, amend or withdraw material contained herein.	
Release	The contributor grants a free, irrevocable license to the IEEE to incorporate material contained in this contribution, and any modifications thereof, in the creation of an IEEE Standards publication; to copyright in the IEEE's name any IEEE Standards publication even though it may include portions of this contribution; and at the IEEE's sole discretion to permit others to reproduce in whole or in part the resulting IEEE Standards publication. The contributor also acknowledges and accepts that this contribution may be made public by IEEE 802.16.	
Patent Policy and Procedures	The contributor is familiar with the IEEE 802.16 Patent Policy and Procedures < http://ieee802.org/16/ipr/patents/policy.html >, including the statement "IEEE standards may include the known use of patent(s), including patent applications, provided the IEEE receives assurance from the patent holder or applicant with respect to patents essential for compliance with both mandatory and optional portions of the standard." Early disclosure to the Working Group of patent information that might be relevant to the standard is essential to reduce the possibility for delays in the development process and increase the likelihood that the draft publication will be approved for publication. Please notify the Chair < mailto:chair@wirelessman.org > as early as possible, in written or electronic form, if patented technology (or technology under patent application) might be incorporated into a draft standard being developed within the IEEE 802.16 Working Group. The Chair will disclose this notification via the IEEE 802.16 web site < http://ieee802.org/16/ipr/patents/notices >.	

Using Quiet Period for Channel Measurement

Shulan Feng

Hisilicon Technologies Co., LTD

Introduction

The current 16h draft has defined the procedure of working channel selecting during initial stage but not considered the detailed procedure in the operating stage. Considering the wireless environment change from time to time, the channels not free in IBS initial stage may be free later, or a channel which is available in the initial stage may be not available because of detection of primary user or overcrowded. So it is perfect if the system in the operating stage listens for the availability of other channels.

On the other hand, system will be quiet during its slave sub-frame, extended quiet period and slave CSI/CMI. These quiet periods are periodic and may be more than 1ms. So it is possible for the system to use these quiet periods to sense the status of another channel or sense the primary user.

Reference

[1] IEEE 802.16h-D1: Air Interface for Fixed Broadband Wireless Access Systems: Amendment for Improved Coexistence Mechanisms for License-Exempt Operation

Proposed Text

15.3.4 Channel measurement during operating stage

System in the operating stage should seek for another idle channel. BS and its associated SSs should use their quiet period to sense another channel. System may be quiet during its slave sub-frame, extended quiet period and non-operating CSI/CMI slot.

BS shall maintenance a table which marks the status of non-operating channels. The channel status may be the value shown in the REP-RSP MAC message.

BS may send the channel number to be measured to its associated SSs in advance using REP-REQ MAC message or measurements IEs in DL-MAP. During the slave sub-frame and the extended quiet period, system, including BS and its associated SSs may switch to the channel to be measured channel to sense if the channel is free.

Furthermore, during the ICSI, BS may switch to the channel to be measured channel and broadcast its interference information on that channel. The SSs on the measured channel will detect this broadcast and report their serving BS. Then the BS working on the measured channel will send IP message to the measurement BS to tell its existence on the measurement channel. This procedure is performed just like community entry procedure of new BS (15.3.1.3) except that there is no need to perform interference avoidance coordination. BS and its neighbor BS on the measured channel just record each other's existence.

Similarly, during the quiet CMI slot, BS may switch to the channel to be measured channel and find a free CMI to broadcast its interference information on that channel just like community entry procedure of new BS

(15.3.2.3) except that there is no need to perform interference avoidance coordination. BS and its neighbor BS on the measured channel just record each other's existence.

If a system finds a free channel and decides to switch to that channel, it will notify its neighbor system of its departure and the MAC frame number when it will leave. The neighbor systems may coordinate with each other and update their sub-frame distribution after channel switching.